

COMP Superscalar

COMPSs at BSC

Supercomputers Manual

VERSION: 2.1 June 15, 2017



This manual only provides information about the COMPSs usage at MareNostrum. Specifically, it details the available COMPSs modules, how to load them and how to create and track COMPSs jobs.

If you want to install COMPSs on your local machine please refer to the *COMPSs* Installation Manual available at our webpage http://compss.bsc.es.

For further information about the application's execution please refer to the *COMPSs* User Manual: Application execution guide available at http://compss.bsc.es.

For further information about the application's development please refer to the *COMPSs* User Manual: Application development guide available at http://compss.bsc.es/.

For full COMPSs example application (codes, execution commands, results, logs, etc.) please refer to the *COMPSs Sample Applications* available at http://compss.bsc.es/

Contents

1	COMP Superscalar (COMPSs)	1
2	Common usage2.1Available COMPSs modules2.2Configuration2.3COMPSs Job submission	2 2 2 3
3	Nord 3 3.1 Basic queue commands	8 8 8
4	MinoTauro 4.1 Basic queue commands . 4.2 Tracking COMPSs jobs .	10 10 10
5	Enabling COMPSs Monitor 5.1 S.1 Configuration 5.2 Execution	12 12 12

List of Figures

1	COMPSs Monitor login for Supercomputers	13
2	COMPSs Monitor main page for a test application at Supercomputers	14

1 COMP Superscalar (COMPSs)

COMP Superscalar (COMPSs) is a programming model which aims to ease the development of applications for distributed infrastructures, such as Clusters, Grids and Clouds. COMP Superscalar also features a runtime system that exploits the inherent parallelism of applications at execution time.

For the sake of programming productivity, the COMPSs model has four key characteristics:

- Sequential programming: COMPSs programmers do not need to deal with the typical duties of parallelization and distribution, such as thread creation and synchronization, data distribution, messaging or fault tolerance. Instead, the model is based on sequential programming, which makes it appealing to users that either lack parallel programming expertise or are looking for better programmability.
- Infrastructure unaware: COMPSs offers a model that abstracts the application from the underlying distributed infrastructure. Hence, COMPSs programs do not include any detail that could tie them to a particular platform, like deployment or resource management. This makes applications portable between infrastructures with diverse characteristics.
- Standard programming languages: COMPSs is based on the popular programming language Java, but also offers language bindings for Python and C/C++ applications. This facilitates the learning of the model, since programmers can reuse most of their previous knowledge.
- No APIs: In the case of COMPSs applications in Java, the model does not require to use any special API call, pragma or construct in the application; everything is pure standard Java syntax and libraries. With regard the Python and C/C++ bindings, a small set of API calls should be used on the COMPSs applications.

2 Common usage

2.1 Available COMPSs modules

COMPSs is configured as a Linux Module. As shown in next Figure, the users can type the module available COMPSs command to list the supported COMPSs modules in the supercomputer. The users can also execute the module load COMPSs/<version> command to load an specific COMPSs module.

```
$ module available COMPSs
------ /apps/modules/modulefiles/tools -----
COMPSs/1.2
COMPSs/1.3
COMPSs/1.4
COMPSs/2.0
COMPSs/2.1
COMPSs/release(default)
COMPSs/trunk
$ module load COMPSs/release
load java/1.8.0u66 (PATH, MANPATH, JAVA_HOME, JAVA_ROOT, JAVA_BINDIR,
SDK_HOME, JDK_HOME, JRE_HOME)
load MKL/11.0.1 (LD_LIBRARY_PATH)
load PYTHON/2.7.3 (PATH, MANPATH, LD_LIBRARY_PATH, C_INCLUDE_PATH)
load COMPSs/release (PATH, MANPATH, IT_HOME)
```

The following command can be run to check if the correct COMPSs version has been loaded:

\$ enqueue_compss --version
COMPSs version <version>

2.2 Configuration

The COMPSs module contains **all** the COMPSs dependencies, including Java, Python and MKL. Modifying any of these dependencies can cause execution failures and thus, we **do not** recommend to change them. Before running any COMPSs job please check your environment and, if needed, comment out any line inside the .bashrc file that loads custom COMPSs, Java, Python and/or MKL modules.

The COMPSs module needs to be loaded in all the nodes that will run COMPSs jobs. Consequently, the module load must be included in your .bashrc file. To do so, please run the following command with the corresponding COMPSs version:

```
$ cat "module load COMPSs/release" >> ~/.bashrc
```

Log out and back in again to check that the file has been correctly edited. The next listing shows an example of the output generated by well loaded COMPSs installation.

Please remember that COMPSs runs in several nodes and your current environment is not exported to them. Thus, all the needed environment variables **must** be loaded through the *.bashrc* file.

2.3 COMPSs Job submission

COMPSs jobs can be easily submitted by running the **enqueue_compss** command. This command allows to configure any **runcompss** option and some particular queue options such as the queue system, the number of nodes, the wallclock time, the master working directory, the workers working directory and number of tasks per node.

Next, we provide detailed information about the *enqueue_compss* command:

```
$ enqueue_compss -h
Usage: enqueue_compss [queue_system_options] [COMPSs_options]
          application_name [application_arguments]
* Options:
  General:
    --help, -h
                                            Print this help message
  Queue system configuration:
    --sc_cfg=<name>
                                            SuperComputer configuration file to use.
                                            Must exist inside queues/cfgs/
                                            Default: default
  Submission configuration:
                                            Expected execution time of the application (in minutes)
     -exec_time=<minutes>
                                            Default: 10
    --num_nodes=<int>
                                            Number of nodes to use
                                            Default: 2
    --num_switches=<int>
                                            Maximum number of different switches.
                                            Select 0 for no restrictions.
                                             Maximum nodes per switch: 18
                                            Only available for at least 4 nodes.
                                            Default: 0
                                            Queue name to submit the job. Depends on the queue
    --queue=<name>
                                             system.
```

	For example (Nord3): bsc_cs bsc_debug debug interactive Default: default
reservation= <name></name>	Reservation to use when submitting the job. Default: disabled
job_dependency= <jobid></jobid>	Postpone job execution until the job dependency has ended. Default: None
storage_home= <string></string>	Root installation dir of the storage implementation Default: null
storage_props= <string></string>	Absolute path of the storage properties file Mandatory if storage_home is defined
Ioursh configuration.	
cpus_per_node= <int></int>	Available CPU computing units on each node Default: 16
gpus_per_node= <int></int>	Available GPU computing units on each node Default: O
max_tasks_per_node= <int></int>	Maximum number of simultaneous tasks running on a node Default: -1
node_memory= <mb></mb>	Maximum node memory: disabled <int> (MB) Default: disabled</int>
network= <name></name>	Communication network for transfers:
	default ethernet infiniband data. Default: infiniband
prolog=" <string>"</string>	Task to execute before launching COMPSs (Notice the quotes). If the task has arguments split them by "," rather than spaces. This argument can appear multiple times for more than one prolog action Default: Empty
epilog=" <string>"</string>	Task to execute after executing the COMPSs application (Notice the quotes). If the task has arguments split them by "," rather than spaces. This argument can appear multiple times for more than one epilog action Default: Empty
master_working_dir= <path></path>	Working directory of the application Default: .
worker_working_dir= <name path="" =""></name>	Worker directory. Use: scratch gpfs <path> Default: scratch</path>
worker_in_master_cpus= <int></int>	Maximum number of CPU computing units that the master node can run as worker. Cannot exceed cpus_per_node. Default: 0
worker_in_master_memory= <int> MB</int>	Maximum memory in master node assigned to the worker. Cannot exceed the node_memory. Mandatory if worker_in_master_tasks is specified. Default: disabled
jvm_worker_in_master_opts=" <string>"</string>	Extra options for the JVM of the COMPSs Worker in the Master Node. Each option separed by "," and without blank spaces (Notice the quotes) Default: Empty

container_image= <path></path>	Runs the application by means of a singularity container image Default: Empty
container_compss_path= <path></path>	Path where compss is installed in the Singularity container image Default: /opt/COMPSs
Runcompss configuration:	
Tools enablers:	
graph= <bool>,graph, -g</bool>	Generation of the complete graph (true/false) When no value is provided it is set to true Default: false
tracing= <level>,tracing, -t</level>	Set generation of traces and/or tracing level ([true basic] advanced false) True and basic levels will produce the same traces. When no value is provided it is set to true Default: false
monitoring= <int>,monitoring, -m</int>	Period between monitoring samples (milliseconds) When no value is provided it is <u>set</u> to 2000 Default: O
external_debugger= <int>, external_debugger</int>	Enables external debugger connection on the specified port (or 9999 if empty) Default: false
Runtime configuration options:	
task_execution= <compss storage></compss storage>	Task execution under COMPSs or Storage. Default: compss
storage_conf= <path></path>	Path to the storage configuration file Default: None
project= <path></path>	Path to the project XML file Default: default_project.xml
resources= <path></path>	Path to the resources XML file Default: default_resources.xml
lang= <name></name>	Language of the application (java/c/python) Default: Inferred if possible. Otherwise: java
summary	Displays a task execution summary at the end of the application execution Default: false
log_level= <level>,debug, -d</level>	Set the debug level: off info debug Default: off
Advanced options:	
extrae_config_file= <path></path>	Sets a custom extrae config file. Must be in a shared disk between all COMPSs workers. Default: null
comm= <classname></classname>	Class that implements the adaptor for communications
	Supported adaptors:
	<pre>integratedtoolkit.nio.master.NIUAdaptor integratedtoolkit.gat.master.GATAdaptor Default: integratedtoolkit.nio.master.NIOAdaptor</pre>
conn= <classname></classname>	Class that implements the runtime connector for
	the cloud
	Supported connectors:
	Default: integratedtoolkit.connectors.DefaultSSHConnector

scheduler= <classname></classname>	Class that implements the Scheduler for COMPSs Supported schedulers: integratedtoolkit.scheduler.fullGraphScheduler .FullGraphScheduler integratedtoolkit.scheduler.fifoScheduler.FIFOScheduler integratedtoolkit.scheduler.resourceEmptyScheduler .ResourceEmptyScheduler Default: integratedtoolkit.scheduler.loadBalancingScheduler .LoadBalancingScheduler
library_path= <path></path>	Non-standard directories to search for libraries (e.g. Java JVM library, Python library, C binding library) Default: Working Directory
classpath= <path></path>	Path for the application classes / modules Default: Working Directory
appdir= <path></path>	Path for the application class folder. Default: User home
base_log_dir= <path></path>	Base directory to store COMPSs log files (a .COMPSs/ folder will be created inside this location) Default: User home
specific_log_dir= <path></path>	Use a specific directory to store COMPSs log files (the folder MUST exist and no sandbox is created) Warning: Overwritesbase_log_dir option Default: Disabled
uuid= <int></int>	Preset an application UUID Default: Automatic random generation
master_name= <string></string>	Hostname of the node to run the COMPSs master Default: None
master_port= <int></int>	Port to run the COMPSs master communications. Only for NIO adaptor Default: [43000,44000]
jvm_master_opts=" <string>"</string>	Extra options for the COMPSs Master JVM. Each option separed by "," and without blank spaces (Notice the quotes) Default: Empty
jvm_workers_opts=" <string>"</string>	Extra options for the COMPSs Workers JVMs. Each option separed by "," and without blank spaces (Notice the quotes) Default: -Xms1024m,-Xmx1024m,-Xmn400m
cpu_affinity=" <string>"</string>	Sets the CPU affinity for the workers Supported options: disabled, automatic, user defined map of the form "0-8/9,10,11/12-14,15,16" Default: automatic
gpu_affinity=" <string>"</string>	Sets the GPU affinity for the workers Supported options: disabled, automatic, user defined map of the form "0-8/9,10,11/12-14,15,16" Default: automatic
task_count= <int></int>	Only for C/Python Bindings. Maximum number of different functions/methods, invoked from the application, that have been selected as tasks Default: 50
pythonpath= <path></path>	Additional folders or paths to add to the PYTHONPATH Default: User home
PyObject_serialize= <bool></bool>	Only for Python Binding. Enable the object

serialization to string when possible (true/false).
Default: false

* Application name:
 For Java applications: Fully qualified name of the application
 For C applications: Path to the master binary
 For Python applications: Path to the .py file containing the main program

* Application arguments: Command line arguments to pass to the application. Can be empty.

3 Nord 3

3.1 Basic queue commands

The Nord3 supercomputer uses the LSF (Load Sharing Facility) workload manager. The basic commands to manage jobs are listed below:

- **bsub** Submit a batch job to the LSF system
- **bkill** Kill a running job
- **bjobs** See the status of jobs in the LSF queue
- **bqueues** Information about LSF batch queues

For more extended information please check the *IBM Platform LSF Command Reference* at https://www.ibm.com/support/knowledgecenter/en/SSETD4_9.1.2/lsf_kc_cmd_ref.html.

3.2 Tracking COMPSs jobs

When submitting a COMPSs job a temporal file will be created storing the job information. For example:

```
$ enqueue_compss \
  --exec_time=15 \setminus
  --num nodes=3 \
  --cpus_per_node=16 \
  --master_working_dir=. \
  --worker_working_dir=gpfs \
  --lang=python \
  --log_level=debug \
  <APP> <APP_PARAMETERS>
SC Configuration:
                            default.cfg
                            default
Queue:
                           disabled
Reservation:
Num Nodes:
                           3
Num Switches:
                           0
GPUs per node:
                           0
Job dependency:
                           None
Exec-Time:
                           00:15
Storage Home:
                           null
Storage Properties:
                           null
Other:
        --sc_cfg=default.cfg
        --cpus_per_node=16
        --master_working_dir=.
        --worker_working_dir=gpfs
        --lang=python
        --classpath=.
        --library_path=.
        --comm=integratedtoolkit.nio.master.NIOAdaptor
        --tracing=false
        --graph=false
        --pythonpath=.
        <app> <app_parameters></a>
Temp submit script is: /scratch/tmp/tmp.pBG5yfFxEo
```

<pre>\$ cat /scratch/tmp/tmp.pBG5yfFxEo</pre>
#!/bin/bash
#
#BSUB -J COMPSs
#BSUB -cwd .
#BSUB -oo compss-%J.out
#BSUB -eo compss-%J.err
#BSUB -n 3
#BSUB -R "span[ptile=1]"
#BSUB -W 00:15
•••

In order to trac the jobs state users can run the following command:



The specific COMPSs logs are stored under the ~/.COMPSs/ folder; saved as a local *runcompss* execution. For further details please check *COMPSs User Manual: Application Execution* available at our webpage http://compss.bsc.es.

4 MinoTauro

4.1 Basic queue commands

The MinoTauro supercomputer uses the SLURM (Simple Linux Utility for Resource Management) workload manager. The basic commands to manage jobs are listed below:

- **sbatch** Submit a batch job to the SLURM system
- scancel Kill a running job
- squeue -u <username> See the status of jobs in the SLURM queue

For more extended information please check the *SLURM: Quick start user guide* at https://slurm.schedmd.com/quickstart.html.

4.2 Tracking COMPSs jobs

When submitting a COMPSs job a temporal file will be created storing the job information. For example:

```
$ enqueue_compss \
  --exec_time=15 \
  --num_nodes=3 \
  --cpus_per_node=16 \
  --master_working_dir=. \
  --worker_working_dir=gpfs \
  --lang=python \
  --log_level=debug \
  <APP> <APP_PARAMETERS>
                           default.cfg
SC Configuration:
Queue:
                           default
Reservation:
                           disabled
Num Nodes:
                           3
Num Switches:
                           0
GPUs per node:
                          0
Job dependency:
                          None
Exec-Time:
                           00:15
Storage Home:
                          null
Storage Properties:
                           null
Other:
        --sc_cfg=default.cfg
        --cpus_per_node=16
        --master_working_dir=.
        --worker_working_dir=gpfs
        --lang=python
        --classpath=.
        --library_path=.
        --comm=integratedtoolkit.nio.master.NIOAdaptor
        --tracing=false
        --graph=false
        --pythonpath=.
        <APP> <APP_PARAMETERS>
Temp submit script is: /scratch/tmp/tmp.pBG5yfFxEo
$ cat /scratch/tmp/tmp.pBG5yfFxEo
#!/bin/bash
#SBATCH --job-name=COMPSs
```



In order to trac the jobs state users can run the following command:

\$ sque	ue							
JOBID	PARTITION	NAME	USER	ST	TIME	NODES	NODELIST	(REASON)
XXXX	projects	COMPSs	XX	R	00:02	3	nvb[6-8]	

The specific COMPSs logs are stored under the ~/.COMPSs/ folder; saved as a local *runcompss* execution. For further details please check *COMPSs User Manual: Application Execution* available at our webpage http://compss.bsc.es.

5 Enabling COMPSs Monitor

5.1 Configuration

As supercomputer nodes are connection restricted, the better way to enable the *COMPSs Monitor* is from the users local machine. To do so please install the following packages:

- COMPSs Runtime
- COMPSs Monitor
- sshfs

For further details about the COMPSs packages installation and configuration please refer to the *COMPSs Installation Manual* available at our webpage http://compss.bsc.es. If you are not willing to install COMPSs in your local machine please consider to download our Virtual Machine available at our webpage.

Once the packages have been installed and configured, users need to mount the sshfs directory as follows. The SC_USER stands for your supercomputer's user, the SC_ENDPOINT to the supercomputer's public endpoint and the TARGET_LOCAL_FOLDER to the local folder where you wish to deploy the supercomputer files):

Whenever you wish to unmount the sshfs directory please run:

compss@bsc:~\$ sudo umount TARGET_LOCAL_FOLDER/.COMPSs

5.2 Execution

Access the COMPSs Monitor through its webpage (http://localhost:8080/compss-monitor by default) and log in with the TARGET_LOCAL_FOLDER to enable the COMPSs Monitor for MareNostrum.

Please remember that to enable **all** the COMPSs Monitor features applications must be ran with the *-m* flag. For further information please check the *COMPSs User Manual: Application Execution* available at our webpage http://compss.bsc.es.

Figure 1 illustrates how to login and Figure 2 shows the COMPSs Monitor main page for an application run inside a Supercomputer.



Figure 1: COMPSs Monitor login for Supercomputers

Barcelona Supercompu Center Centro Nacional d	Iting COMPSS MONITOR												FAQ Configuration		
s <	Resources Information	Tasks information	Current tasks graph	Complete tasks graph	Load chart	Runtime log	Execution Informatic	on Statistics							
i i	Status	Resource Nam	e	CPU Computing Units	GPU Compu	ing Units FPG	A Computing Units	OTHER Computing Unit	ts Memory Size	Disk Size	Provider	Image	Running Actions		
Refresh		s04r2b83		16					28.0 GB	- GB			195 203 387 395 355 443 411 403 379 324 363 427 435 371 348		
		s04r2b80		16					28.0 GB	- GB			226 210 218 275 315 299 339 307 283 259 267 331 243 251 292		

Figure 2: COMPSs Monitor main page for a test application at Supercomputers

Please find more details on the COMPSs framework at http://compss.bsc.es